

## HOW TO GERMINATE MILKWEEDS

MILKWEEDS (*ASCLEPIAS* spp.) ARE NOTORIOUSLY DIFFICULT TO GERMINATE. But don't despair. The Wildflower Center has developed and tested a protocol that results in good germination rates for a number of our native milkweed species. Follow this process and you'll soon be on your way to supporting monarchs, bumblebees and tons of other insects that depend on milkweed plants.



### 1. COLLECT MATERIALS

*Here are the materials you'll need to get started:*

- Milkweed seeds native to your specific ecoregion
- A plastic bag with a seal or zip closure
- A bulb growing tray or other large, shallow container with drainage holes
- Numerous 4-inch pots
- Stratification mix (one part perlite to one part vermiculite)
- Seed germinating mix (can be found at garden centers or nurseries)
- Well-draining growing mix. Wildflower Center experts have successfully used several different growing mixes:
  - One part coarse sand to one part compost, or
  - One part coconut coir to one part coarse sand to one part compost, or
  - Composted pine bark (can add coarse sand)



### 2. SOAK AND STRATIFY SEEDS

*Milkweed seeds require some time in the damp cool.*

- Soak milkweed seeds in water for several hours or overnight; tap water is okay.
- After the seeds have soaked, put them in a sealed plastic bag filled with moist stratification mix (and by "moist" we mean like a damp sponge, no excess water).
- Refrigerate the bag of moist seeds in their mix for at least two weeks. For some species of *Asclepias*, 30 days of cool moist stratification yields 85 percent germination or better.
- Check your seeds every day or so; some seeds such as *A. incarnata* and *A. tuberosa* may begin to germinate in the bag.



### 3. GERMINATE

*Once cold stratified, your milkweed seeds are ready to germinate.*

- Transfer moist seeds and stratification mix into a bulb tray (or similar) of damp but not soggy germinating mix.
- Cover lightly with germinating mix.
- Mist to moisten soil surface thoroughly and check daily.
- As seeds germinate, mist occasionally. If they are kept in a germinating mix that is too moist, the seedlings will "damp off," which means they'll die. Good air movement reduces the potential for damping off, so if the weather is mild or warm, move the bulb tray outdoors under bright, indirect light.



### 4. TRANSPLANT

*Those little seedlings are growing up! Time for them to move out on their own.*

- Once the seedlings have one or more sets of true leaves, gently transplant them into 4-inch pots or 5-inch liners filled with well-draining growing mix.
- Center Propagation Specialist Susan Prosperie advises leaving seedlings in pots for at least six weeks (until they grow enough roots to survive) and transplanting them into the ground in fall or spring.

***So what are you waiting for? Go ahead and get growing!***